Subject: Paragraphs and Headers

From: "Matt Knowles" < <u>matt@aestheticdesign.com</u>>

Sent: 4/3/2020 9:45:21 AM

To: "Jim Beck" < <u>jim@patchencalifornia.com</u>>;

Now that all of your sites are running the same theme, I'll start answering your questions using <u>patchencalifornia.com</u> as an example, unless your question directly relates to a page on another site. Unless the question that relates to a plugin that isn't installed on all of the sites, then the answer should apply to all 5.

I'm going to tackle each question individually so we can make my answer makes sense before going on to the next one. I will also change the subject header of the email to that topic to make it easier for you to refer back to if you have questions again later.

A lot of knowing how these options work will require that you have an understanding on how inheritance works, and that you understand the basic box model of html. If I just lost you there, let me know and I'll give you a quick tutorial on those two concepts.

Since we both don't care for the customizer, I'll provide the alternative way to do it if there is one. There are some things you have to configure in the Appearance->Customize, some you have to do through the Appearance->Weaver Xtreme Admin, and some you can do through both interfaces.

https://patchencalifornia.com/about-us/contact-us/

Within a given Site is it possible to change the definition of Paragraph, Heading 1, Heading 2, etc.?


To set the default font size, go to Main Options->Fonts & Custom and scroll down to the Fonts section. There you can set the size, and the line height which is the spacing between lines in a paragraph.

A Fonts 0	Font Base Sizes
Site Base Font Size: 16 px	Base font size of standard text. This value determines the default medium font size. Note that visitors can change their browser's font size, so final font size can vary, as expected. (Default: 16px)
Site Base Line Height:	Set the Base line-height. Most other line heights based on this multiplier. (Default: 1.5 – no units) (★Plus)
Site Base Font Size - Small Tablets:	Small Tablet base font size of standard text. (Default medium font size: 16px) (★Plus)
Site Base Font Size - Phones: px	Phone base font size of standard text. (Default medium font size: 16px) (★Plus)
Custom Font Size A: em	Specify font size in em for Custom Size A (★Plus)
Custom Font Size B: em	Specify font size in em for Custom Size B (★Plus)
Disable Google Font Integration:	ADVANCED OPTION! Be sure you understand the consequences of this option. By disabling Google Font Integration, the Google Fonts definitions will not be loaded for your site. Please note : Any previously selected Google Font Families will revert to generic serif, sans, mono, and script fonts.

Once you've set the standard size, all the other sizes are usually based off of that as a percentage by default.


The paragraph, Heading 1, etc are defined in the sections under Main Options->Content Areas for the area's of the site that you should be concerned with.

For the standard paragraph text this area allows you to define the color, size, padding and margins.



The Page Title should is automatically styled as H1, and any headings that you add in your content should be h2 or higher.

If you want o configure the Page Title, use that section to do it.



For h2 thru h4 (I've never found the need to past h4) the default font size is calculated

and the other styling is predefined in the stylesheet for that particular sub-theme.

If you want to change how the h2 thru h4 headers look, it is best to send me an email with what changes you want and I'll add an override for the style sheet. That will keep it consistent throughout that site. There's no easy interface to change those in Weaver Xtreme. The older theme Weaver II had a page that made it easier to add css for individual elements, but that has disappeared in Xtreme.

Matt Knowles
Aesthetic Design & Photography
www.aestheticdesign.com
707-786-4643